

Version 1.1

USER MANUAL

RIECADO eAuctionyzer Version 1.1

LEGAL NOTES

Microsoft, MS, MS-DOS and Windows are trademarks of the Microsoft Corporation.

It is not allowed to pass on or copy this document. The use of the content has to be permitted.

Acting against claims damages.

All rights reserved, especially in case of taking out a patent.

The screenshots serve as samples and do not bind to a special functionality.

Technical subject to change without prior notice.

ISSUED BY:

RIECADO GmbH

Regional Energy Capacity Auction Data Operator Gesellschaft
m.b.H.

Palais Liechtenstein
Alserbachstraße 14-16, A-1090 Vienna,

T: +43-(0)1-319 07 01 Fax Ext 70

E: office@riecado.at

W: www.riecado.at

DOCUMENT MANAGEMENT

Permission to Change

Stefan Hartlieb	RIECADO GmbH	Wien
Andreas Wolf	RIECADO GmbH	Wien

Document Status:

Final

Document- History

VERSION	STATUS	DATE	RESPONSIBLE	REASON FOR CHANGE
0.1	Completed	20.07.2010	Stefan Hartlieb	Finishing 0.1 Beta
0.2	Completed	18.11.2010	Stefan Hartlieb	Finishing 0.2 Beta
1.0	Completed	17.12.2010	Stefan Hartlieb	Release 1.0
1.1	Completed	22.03.2011	Stefan Hartlieb	Release 1.1

TABLE OF CONTENTS

01	INTRODUCTION	8
01.1	Target Group	8
01.2	Writing Conventions	8
01.3	General Principles and User Guidance	8
01.3.1	Navigation	8
02	INSTALLATION AND SYSTEM REQUIREMENTS	9
02.1	System Requirements	9
02.1.1	Program Requirements	9
02.1.2	Operating System	9
02.1.3	Free Harddiskspace	9
02.2	Installation of eAuctionyzer on Windows Computers	9
02.3	Update of eAuctionyzer	10
02.4	Installation of GAMS	10
02.4.1	Installation	10
02.4.2	GAMS License	10
02.4.3	Integration of GAMS	10
02.5	License of the Software	11
02.5.1	Shipping License	11
02.5.2	Request a License	11
02.5.3	Extend the License	11
03	APPLICATION DESCRIPTION	12
03.1	Program Startup	12
03.2	PTDF	12
03.2.1	PTDF Import	12
03.2.2	PTDF Filename and Layout	12
03.2.3	Overview on the imported PTDF's	13
03.2.4	PTDF Comparison	14
03.2.5	PTDF Search	17
03.3	Bid Scenarios	18
03.3.1	Bid Scenario Layout	18
03.3.2	Generate a New Bid Scenario	19
03.3.3	Save and Delete Bid Scenarios	22
03.3.4	Duplicate a Bid Scenario	22
03.3.5	Search and Select a Bid Scenario	22
03.3.6	Bid Generator	23
03.4	Auction – Auction Scenarios	25
03.4.1	Set Up an Auction Scenario	25
03.4.2	Open a Saved Auction Scenario	28
03.5	Results	28

03.5.1	Element Selections	29
03.5.2	Select the View	29
03.6	Sensitivity Analysis	34
03.6.1	Setup of Sensitivity Analysis	35
03.6.2	Run of Sensitivity Analysis	35
03.6.3	Open a Calculated Sensitivity Analysis	35
03.6.4	Delete a Sensitivity Analysis / a Sensitivity Analysis Scenario	35
03.6.5	Sensitivity Analysis Results	35
03.7	Data Management and Presettings	37
03.7.1	Manage the Market Areas	37
03.7.2	Market Prices	37
03.7.3	Products	38
03.7.4	Predefine Import and Export Limits	38
03.7.5	Predefine Import Paths	39
03.8	Other Functionality	39
03.8.1	Export the Shown Tables	39
03.8.2	Block Functionality	39
04	CONTACT INFORMATION	41
APPENDIX A – STATISTIC METHOD DESCRIPTION		42
APPENDIX B – CALUCLATION TIMES		45
APPENDIX C – SHORT TERMS		46

TABLE OF FIGURES

FIGURE 1: NAVIGATION BAR	8
FIGURE 2: INSTALLATION OF EAUCTIONYZER	10
FIGURE 3: INTEGRATING GAMS PATH	10
FIGURE 4: REGISTRY AND LICENSE SCREEN	11
FIGURE 5: PTDF IMPORT SCREEN AFTER PRESSING SEARCH	12
FIGURE 6: PTDF MATRIX	13
FIGURE 7: PTDF LIST VIEW	14
FIGURE 8: PTDF VIEW	14
FIGURE 9: PTDF ONE SOURCE TO ONE SINK VIEW	15
FIGURE 10: PTDF TABLE VIEW FOR ONE SOURCE TO ALL SINKS	15
FIGURE 11: PTDF GRAPH VIEW FOR ALL SOURCES TO ONE SINK	16
FIGURE 12: PTDF TABLE VIEW FOR SELECTED BORDERS	16
FIGURE 13: PTDF GRAPH VIEW FOR SELECTED BORDERS	17
FIGURE 14: PTDF SEARCH VIEW IN COMBINATION WITH THE 1 TO ALL VIEW	18
FIGURE 15: EMPTY BID SCENARIO EDITION VIEW	19
FIGURE 16: IMPORT BIDS TO A SCENARIO BY PRESSING "IMPORT"	20
FIGURE 17: PART OF A POSSIBLE BID IMPORT FILE	20
FIGURE 18: FULL BID SCENARIO EDITION VIEW	21
FIGURE 19: BID LIST VIEW	21
FIGURE 20: BID SCENARIO SELECTION VIEW	23
FIGURE 21: BID GENERATOR WITH PATH WISE VIEW	24
FIGURE 22: BID GENERATOR WITH REGION WIDE VIEW	24
FIGURE 23: MINIMIZED AUCTION FLOW SCREEN	25
FIGURE 24: AUCTION FUNCTIONALITY PANEL	25
FIGURE 25: PTDF SELECTION PANEL	26
FIGURE 26: BID SCENARIO SELECTION PANEL	26
FIGURE 27: IMPORT / EXPORT LIMIT SELECTION PANEL	27
FIGURE 28: AUCTION SCENARIO SCREEN WHILE CALCULATION	27
FIGURE 29: AUCTION SCENARIO SCREEN AFTER CALCULATION	27
FIGURE 30: AUCTION SCENARIO SAVE SECTION	27
FIGURE 31: AUCTION SCENARIO LIST	28
FIGURE 32: RESULT VIEW	29
FIGURE 33: SELECTION REGION AT RESULT VIEW	29
FIGURE 34: RESULT TABLE VIEW FOR THE BIDS	30
FIGURE 35: RESULT GRAPH VIEW FOR THE BIDS	31
FIGURE 36: RESULT VIEW FOR THE PATHS	31
FIGURE 37: RESULT VIEW FOR ONE SOURCE AND ALL SINKS	32
FIGURE 38: RESULT VIEW FOR ALL SOURCES AND ONE SINK	32
FIGURE 39: RESULT VIEW FOR THE FULL PATH RESULTS	33

FIGURE 40: RESULT VIEW FOR THE PRODUCTS	34
FIGURE 41: SUMMING AT RESULT VIEW	34
FIGURE 42: SENSITIVITY ANALYSIS PANEL OF AN AUCTION SCENARIO	34
FIGURE 43: SENSITIVITY ANALYSIS RESULT PANEL WITH THE STEP COMPARISON PATH VIEW	36
FIGURE 44: MARKET AREA MANAGEMENT	37
FIGURE 45: MARKET PRICE MANAGEMENT	38
FIGURE 46: PRODUCT LIST	38
FIGURE 47: STANDARD IMPORT AND EXPORT LIMITS	39
FIGURE 48: STANDARD PATH DEFINITION VIEW	39
FIGURE 49: BLOCKED BID SCENARIO	40
FIGURE 50: SCHEMATIC ILLUSTRATION OF A FLAT DISTRIBUTION	42
FIGURE 51: SCHEMATIC ILLUSTRATION OF A NORMAL DISTRIBUTION	43
FIGURE 52: SCHEMATIC ILLUSTRATION OF A CONVEX DISTRIBUTION	43
FIGURE 53: SCHEMATIC ILLUSTRATION OF A CONCAVE DISTRIBUTION	44
FIGURE 54 : OVERVIEW ON CALCULATION TIMES	45

01 INTRODUCTION

This manual describes the usage of the eAuctionyzer for market analysis of load flow based capacity auctions in CEE (Central Eastern Europe) region. This manual conducts all installation processes, proceedings and the analysis.

01.1 Target Group

The target group for the eAuctionyzer are market participants (user) of ECAMT (Enhanced Capacity Auction Management Tool) which is in use for CEE CAO (Central Auction Office) located in Freising.

01.2 Writing Conventions

Buttons that have to be clicked by the user are underlined in the text.

Names and terms are under quotation marks.

“drop-down”: by clicking with the mouse cursor on a drop down selection combo box a list box is displayed to see all available choices. Select one of the items. The selected item remains visible in the assigned field.

The “screenshots” help to visualize the verbal description. The enclosed data may not coincide with real data.

01.3 General Principles and User Guidance

01.3.1 Navigation


01.3.1.1 Navigation Menu

The navigation menu is located on the left side. The navigation menu contains menu items to access the available main functions of the application. For several entries corresponding sub menus exist which will be viewable by clicking on the desired menu point. The navigation can be used independently from the previously used functionality.

01.3.1.2 Navigation Bar

For selecting the relevant menu choose the respective link in the navigation bar on the left hand side. Afterwards select the corresponding link in the sub menu.

Figure 1: Navigation bar



02 INSTALLATION AND SYSTEM REQUIREMENTS

02.1 System Requirements

02.1.1 Program Requirements

eAuctionyzer is designed with Java (www.java.com). To run eAuctionyzer Java version 6 is needed. Java is platform independent and preinstalled under Windows (from Windows XP on). If it is not installed at your operating system go to the webpage, download it and follow the installation instructions.

The shown graphs in eAuctionyzer are done with Flash. If it's not preinstalled go to the webpage (get.adobe.com/de/flashplayer/), download it (Adobe Flash Player for Windows Internet Explorer) and install it on your computer. Otherwise the graphs will not be shown.

02.1.2 Operating System

eAuctionyzer is tested under different Windows platforms (XP, Vista, 7) and an operation on these systems is assured. On older Windows platforms or other operating systems (MAC or Linux) the software is not tested and should not be used.

02.1.3 Free Hard disk space


The program kernel and execution files will take about 30 MB of hard disk space. More space than the program files the computation data - bid scenarios (03.3), PTDFs (03.2) and auction scenarios (03.4) - will take. An average PTDF matrix (with 1500 branches) has about 300 KB, a bid scenario with 1000 bids per product 900 KB. In that case the data for a day (for each hour a PTDF (=24 PTDFs) and one scenario) will be 8 MB, for a month (30 times a day) it will be 240 MB and for a year (365 times a day) 3GB. Also the sensitivity analysis will take a lot of disc space.

PLEASE ENSURE THAT THERE IS ENOUGHT FREE HARDDISC SPACE FOR THE DATA!

02.2 Installation of eAuctionyzer on Windows Computers

- eAuctionyzer does not need any specific installations.
- The program and the corresponding data are sent to eAuctionyzer users (by email) in a self extracting zip format. (www.winzip.com)
- Save the given File (eAuctionyzer_install_1.x.exe) to the local file-system.
- Run the file and select an installation directory and press Unzip (Figure 2).
- eAuctionyzer can now be started by running the file "eAuctionyzer.jar" under the installation directory.
- The functionality of the software will only be available after licensing the software (see 02.5)

Figure 2: Installation of eAuctionyzer



02.3 Update of eAuctionyzer

If a previous version of eAuctionyzer is running on your system please copy the file "eAuctionyzer_update_1.x.exe" to the installation directory. After running the file your version of eAuctionyzer will be updated to version 1.x. All previous data will be available.

02.4 Installation of GAMS

02.4.1 Installation

Auctions are calculated on the basis of an external program called "GAMS" (www.gams.com). For installing GAMS go to the webpage and follow the installation instructions (<http://www.gams.com/dd/docs/gams/win-install.pdf> [2011/03/01]). The installation of GAMS (Version 23.5) needs about 320 MB of free hard disk space.

At the first start of eAuctionyzer GAMS has to be integrated to the system (see 02.4.3).


02.4.2 GAMS License

With eAuctionyzer also a GAMS license is provided (GAMS Run Time Base Module/CPLEX MIP). The depending license file (gamslice.txt) is sent to you with the program data. During the GAMS installation (at point 2 "Copy the GAMS license file") select the provided license file (gamslice.txt).

02.4.3 Integration of GAMS

To integrate this functionality the "gams.exe" has to be assigned. Therefore go to Setting and Setting (Figure 3). By Selecting next to "GAMS path" the file-system opens and the "gams.exe" (usually under C:\Program Files\Gams<##>\gams.exe, the installation directory of GAMS, see 02.4.1) can be selected. With a click on Save the changes will be submitted.

Figure 3: Integrating GAMS path



02.5 License of the Software

02.5.1 Shipping License

eAuctionyzer is shipped with **no** guilty license. No functionality will be available. A license has to be applied for. Therefore go in eAuctionyzer to Setting License (Figure 4). At an update there is no need to apply for a new license. The license of the previous version will be kept.

02.5.2 Request a License


A license can be requested under Setting License.

- Fill in the personal data.
- Press Generate Registry File. This opens the local file-system and the registry file can be stored anywhere at the local system.
- Send this file to **tradertool@riecado.at !!!**
- By the given data RIECADO generates a license file (e.g. filename <name>_license.lic) with an expiration date in case of a temporary license and sends it back to the given email.
- By Search under "Import license file" the file can be selected.
- By Install the license will be installed.
- The status of the license or the expire date can be seen under "Actual license information" at Figure 4.

02.5.3 Extend the License

If there is the need to extend the license (e.g. the expire date has pasted by) repeat the steps in 02.5.2. You will get a new license file with a new expiration date from RIECADO.

Figure 4: Registry and license screen



03 APPLICATION DESCRIPTION

03.1 Program Startup

To start the eAuctionyzer go to the installation directory (see 02.2) and run the file "eAuctionyzer.jar". The program starts, loads the general data and shows the "Startup" screen. To get to the requested program functionality use the navigation bar (see 01.3.1).

At the first startup please register / apply for a license (see 02.5) and set the GAMS path (see 02.4.3)


03.2 PTDF

PTDFs (Power Transfer Distribution Factors) are used for the auction and stored in matrices. The PTDFs are published by the CAO on their webpage.

03.2.1 PTDF Import

To import a PTDF matrix the "Import PTDF from local system" screen has to be called (Figure 5). Therefore press in the navigation PTDF and then Import on the left. It is possible to import one PTDF as csv-file or multiple PTDFs via one zip-file. By clicking Search the file-system opens and a .csv or .zip file can be selected. Via Import the file(s) will be imported into the system.

Figure 5: PTDF import screen after pressing search



03.2.2 PTDF Filename and Layout

The filename of the imported PTDF defines the auction type and the date a PTDF is designed for. Depending on the auction type the filename has to contain the following signs:

- _Y<YYYY>_ for a yearly auction,
- _M<YYYYMM>_ for a monthly auction and
- _<YYYYMMDD>_<HHMM>_2D<DayNumber(1-7)>_ for a daily hourly auction.

As example the published PTDF (from CEE CAO) for the first hour of the first of April 2010 is called (Public_20100401_0000_2D4_CEE0.csv).

The file itself includes a header line and the technical parameter lines. The header must be:

Critical Branch; Case; Source; Sink; TMF; AMF+; AMF-; Factors (SOURCE->SINK)

Figure 6 shows a part of a PTDF matrix.

Figure 6: PTDF matrix


Critical Branch	Case	Source	Sink	TMF	AMF+	AMF-	MAVIR->PSEO	MAVIR->ELES	PSEO->MAVIR	PSEO->ELES	ELES->MAVIR	ELES->PSEO
LINE_00001	n-0	APG	ELES	360.1	276.2	404.1	-0.0159	0.1048	0.0159	0.1207	-0.1048	-0.1207
LINE_00001	n-1 LINE	APG	ELES	360.1	280.4	399.9	-0.0173	0.1155	0.0173	0.1328	-0.1155	-0.1328
LINE_00003	n-0	CEPS	CEPS	1369	629.9	1486	-0.0446	-0.0028	0.0446	0.0418	0.0028	-0.0418
LINE_00003	n-1 LINE	CEPS	CEPS	1369	288.6	1693	-0.0671	-0.0159	0.0671	0.0512	0.0159	-0.0512
LINE_00003	n-1 LINE	CEPS	CEPS	1369	620.1	1493	-0.0481	-0.0032	0.0481	0.0449	0.0032	-0.0449
LINE_00003	n-1 LINE	CEPS	CEPS	1369	570.3	1523	-0.0485	-0.0042	0.0485	0.0444	0.0042	-0.0444
LINE_00003	n-1 LINE	CEPS	CEPS	1369	620.5	1493	-0.0504	-0.0029	0.0504	0.0475	0.0029	-0.0475
LINE_00003	n-1 LINE	CEPS	CEPS	1369	615.7	1494	-0.0423	0.0012	0.0423	0.0435	-0.0012	-0.0435
LINE_00009	n-0	CEPS	CEPS	1368.5	778.2	1337	-0.0446	-0.0028	0.0446	0.0418	0.0028	-0.0418
LINE_00009	n-1 LINE	CEPS	CEPS	1368.5	718.8	1374	-0.0485	-0.0042	0.0485	0.0444	0.0042	-0.0444
LINE_00007	n-0	PSEO	CEPS	1392.6	927.1	1409	-0.2004	-0.0059	0.2004	0.1944	0.0059	-0.1944
LINE_00007	n-1 LINE	PSEO	CEPS	1392.6	751.8	1521	-0.2609	-0.0131	0.2609	0.2478	0.0131	-0.2478
LINE_00004	n-0	CEPS	CEPS	1222.5	299.9	1557	-0.0516	-0.0301	0.0516	0.0215	0.0301	-0.0215
LINE_00004	n-1 LINE	CEPS	CEPS	1222.5	30.6	1671	-0.0704	-0.0313	0.0704	0.0392	0.0313	-0.0392
LINE_00004	n-1 LINE	CEPS	CEPS	1222.5	276.3	1571	-0.059	-0.031	0.059	0.0281	0.031	-0.0281
LINE_00004	n-1 LINE	CEPS	CEPS	1222.5	250.3	1613	-0.0507	-0.031	0.0507	0.0198	0.031	-0.0198
LINE_00004	n-1 LINE	CEPS	CEPS	1222.5	453.9	1466	-0.0418	-0.0265	0.0418	0.0152	0.0265	-0.0152
LINE_00004	n-1 LINE	CEPS	CEPS	1222.5	92.9	1609	-0.0704	-0.0313	0.0704	0.0392	0.0313	-0.0392
LINE_00004	n-1 LINE	CEPS	CEPS	1222.5	276.8	1572	-0.0651	-0.0305	0.0651	0.0346	0.0305	-0.0346

03.2.3 Overview on the imported PTDF's

The imported PTDFs can be shown at "PTDF list view" via [PTDF](#) and [List](#). The PTDFs are split up into different auction types. Depending on the pressed button ([Day](#), [Month](#) or [Year](#)) only the PTDFs for this auction type are shown. At [Day](#) a date has to be selected by the calendar and afterwards it is possible to define a more specific time span. Only the PTDFs for this day that lie between the start and the end time are displayed. For monthly and yearly PTDFs only a period of time has to be defined.


A PTDF can be selected by clicking on it in the list. Primary the quick information for the PTDF is shown. Figure 7 illustrates the selection model for daily auctions, the list with the matching PTDFs and the quick information for the selected PTDF (2011/2/11 H07).

Figure 7: PTDF list view



By clicking **Show PTDF** (Figure 7) the full information for the PTDF can be shown (Figure 8). This view includes the calculation of the maximum (none simultaneously) available capacities if capacities are allocated on different paths. Therefore at "Assumed simultaneously fixed capacities" the (assumed) allocated capacities can be defined. The impact on the (assumed) allocated capacities on the still (none simultaneously) available capacities is shown in the matrix "Free non-concurrent transmission capacity". If a value in this matrix is shown in red the input of the allocated capacities is invalidate.

Figure 8: PTDF view



03.2.4 PTDF Comparison

Another feature of the PTDF analysis is the comparison of different PTDFs (especially their capacities). Four different views are available:


- one source to one sink (1 to 1) (single path)
- one source to all sinks (1 to all) (export capacities)
- all sources to one sink (all to 1) (import capacities)
- all sources to all sinks (all to all) (selected paths)

These views illustrate the changes at the PTDFs over the course of time.

03.2.4.1 1 to 1 View

The one to one view shows the changes of the capacities on the selected path. By selecting a market area as source area and one as sink area the capacities for the selected PTDFs are shown in a table. Figure 9 shows the view for PSEO as source, DE_AT as sink and the selected PTDF-matrices.

Figure 9: PTDF one source to one sink view



03.2.4.2 1 to all & all to 1 View

The one to all view shows all exports from the market area selected as source, the all to one view all imports to the market area selected as sink. In the table the capacities for each path are shown if no concurrency exists. By clicking the button switch the values can be shown as interactive graph. Figure 10 shows the table screen of the one to all view and Figure 11 the graph for the all to one view.

Figure 10: PTDF table view for one source to all sinks





Figure 11: PTFD graph view for all sources to one sink



03.2.4.3 All to all View

At the all to all view the shown paths can be specified. In the upper section of the view the shown borders can be defined. By selecting different market areas as source and sink areas the available borders are shown next. These borders can be selected or deselected and only the data for the selected borders are shown in the table. By pressing switch the data can be shown in a graph. Figure 12 shows the data of the all to all view in a table and Figure 13 the belonging graph.

Figure 12: PTFD table view for selected borders





Figure 13: PTDF graph view for selected borders




03.2.5 PTDF Search

If it is not known for which dates or auction types PTDFs really exist there is also the possibility to search for them. There can be switch between list and search at the upper section of the list side of the "PTDF List View". By clicking Search the search functionality will be opened. Afterwards two dates can be selected. All PTDFs that lie between these two dates are shown in the "Available PTDFs List". There is also the possibility to show only the yearly, monthly or daily PTDFs.

In the middle section the "Available PTDFs List" is shown. There you can see all PTDFs that match the given search criteria's. By selecting the PTDFs and pressing Add they will bid added to the "Selected PTDFs List" in the lower section of the view. All selected PTDFs will be shown in the "PTDF Comparison Views" (see 03.2.4). This gives the user not only the possibility of searching for the PTDFs but also of comparing PTDFs of different days and auction types. Figure 14 shows the PTDF search view in combination with the graph of the one to all view for PTDFs of different days and auction types.

Figure 14: PTFD search view in combination with the 1 to all view



03.3 Bid Scenarios

A bid scenario defines a bidding structure / strategy for an auction.

03.3.1 Bid Scenario Layout

A bid scenario includes a name, a list of tags, dates, the bids split by the products and a flag for own or market scenario.

03.3.1.1 Tag

“Tags” are descriptions that can be free assigned and are designed for facilitating the search (e.g. summer, sunny, sunday, windy, cold, ...).

03.3.1.2 Date

“Dates” must be allocated to show that the scenario is dedicated to a specific day. If no date is allocated, the scenario will not be selectable at the auction scenario screen (see 3.4).

03.3.1.3 Product

“Products” are individual auction availability elements which can be bid for. In a bid scenario there can be bids for daily products (e.g. H01, H02), bids for monthly or yearly auctions are signed by the product BASE. Further information on the products are described at 03.7.3.

03.3.1.4 Own Bid Scenario

The flag “Own bid scenario” defines whether a scenario simulates a market behavior or the own bids. As described later, auctions (see 03.4.1.2) can be calculated with more than one bid scenario. The idea is to take one scenario for market behaviors and one to simulate the own strategy. At the results (see 03.5) the different scenarios can be analyzed separately.

03.3.1.5 Bid

Each bid includes product, source, sink, capacity and price. All bids together define a bidding scenario.

03.3.1.6 Auctions Used

The auctions used shows in which auction scenario the bid scenario is used for. If a bid scenario is used in an auction scenario the bid structure cannot be changed anymore. This is a matter of keeping the data consistent because if the bid structure changes the results of each auction this bid scenario is used will change too and the results will not be guilty anymore until they are new calculated.

03.3.2 Generate a New Bid Scenario

A new bid scenario will be generated by going to Bid Scenario at the navigation bar and then to New. This opens an empty "Bid scenario edition view" (Figure 15).

Figure 15: Empty bid scenario edition view

03.3.2.1 Entering the Bid Scenario Characteristics

At first the bid scenario characteristic information is entered. These are the name, tags and dates. The flag for own bid scenario can be set too.


Tags can be inserted by writing them next to "Tag" and afterwards press Add or the RETURN-key. Multiple elements can be inserted with ';' as separator. For deleting the element, it has to be selected at "Dedicated" and then pressed Delete. Dates are added by opening the calendar selecting a date and pressing Add next to the field.

03.3.2.2 Add Bids to a Scenario

After defining the characteristic information, bids can be added to the scenario. You may add single bids (described at 03.3.2.4), generate bids with the bid generator (see 03.3.6) or import whole strategies from .csv files.

To import a whole strategy the button Import has to be pressed. The file-system opens and a .csv file can be selected (Figure 16).

Figure 16: Import bids to a scenario by pressing "Import"



03.3.2.2.1 Layout of a Bid File

A bid file has a header line and the bid lines. The header line has to contain:

Source; Sink; Product; Volume (or Capacity); Price (or Preis)

Source and **sink** are either market areas or zones. At import zones will be converted to the corresponding market area. Not defined market areas or zones (see 03.7.1) will be ignored.

Product should be a common used product (H01 to H24 or BASE). If the product is not defined (see 03.7.3) the entry of the file will be ignored.

The **volume** is the amount of power and has to be in whole numbers in MWh.

The **price** is the amount of money in Euro per MW and hour (€/MWh). The comma separator is either a "." or a ",". No thousands separator is used. The price and the volume must be positive.

Figure 17: Part of a possible bid import file

Product	Source zone	Sink zone	Capacity	Angebotspreis [EUR/MWh]		
H24	APG	CEPS	85,00	0,01		
H23	APG	CEPS	85,00	0,01		
H22	APG	CEPS	85,00	0,01		
H21	APG	CEPS	85,00	0,01		
H20	APG	CEPS	85,00	0,01		
H19	APG	CEPS	85,00	0,01		
H18	APG	CEPS	85,00	0,01		
H17	APG	CEPS	85,00	0,01		
H16	APG	CEPS	85,00	0,01		
H15	APG	CEPS	85,00	0,01		
H14	APG	CEPS	85,00	0,01		
H13	APG	CEPS	85,00	0,01		
H12	APG	CEPS	85,00	0,01		
H11	APG	CEPS	85,00	0,01		
H10	APG	CEPS	85,00	0,01		
H09	APG	CEPS	85,00	0,01		
H08	APG	CEPS	85,00	0,01		
H07	APG	CEPS	85,00	0,01		
H06	APG	CEPS	85,00	0,01		
H05	APG	CEPS	85,00	0,01		
H04	APG	CEPS	85,00	0,01		
H03	APG	CEPS	85,00	0,01		
H02	APG	CEPS	85,00	0,01		
H02	ELES	APG	20,00	0,51		
H02	ELES	APG	5,00	0,47		
H02	ELES	APG	10,00	0,45		
H02	ELES	APG	5,00	0,38		
H02	ELES	APG	5,00	1,15		
H02	ELES	APG	50,00	1,02		
H02	ELES	APG	10,00	0,97		

The order of the columns is irrelevant as well as additional text in the header fields or additional columns. After the import of the bids the quick view for the bids are re-calculated. The quick view includes a bid count per product as well as path information

that can be shown for each product. The path information is split up into three matrices, first showing the bid count, second the requested volume and the third the average price of the bids for each path.

The three matrices (Figure 18 on the right side) present the bid count, the requested volume and the average price of the bids for each path.

If lines or elements are ignored in case of inconsistent data an information will be displayed after the import.

Figure 18: Full bid scenario edition view

03.3.2.3 Show the Bids

All bids can be shown in a table by pressing **Show** at the bid scenario editing screen (Figure 18). The "Bid list view" will be displayed (Figure 19). For each bid product, source, sink, requested volume and price is shown. The bids are sorted alphabetically by product, source, sink and at last by descending prices. The bids can be filtered by products. Only the bids attributed by the selected products in the list are presented.

Figure 19: Bid list view

03.3.2.4 Add Single Bids

A single bid can be added at the bottom part of the "Bid list view" (Figure 19). By selecting product, source and sink, inserting volume and price and afterwards click on Add, a bid will be added to the list. Source and sink must be different and the volume and the price greater than zero. The list will be reordered (see 03.3.2.3).

03.3.2.5 Delete Bids

Bids can be deleted by selecting the bids at „Bid list view“ and click on Delete next to the table. All selected bids will be deleted.

03.3.2.6 Export the Bid List

The shown bids in the bid list can be exported as .csv-file to the local file system. By pressing Save As the local file system opens and a save directory can be selected.

03.3.3 Save and Delete Bid Scenarios

A bid scenario or the entered changes are saved through a click on Save at the "Bid scenario edit view" (Figure 18). Only after this action, the changes will be committed. Leaving the screen by pressing Back or a button in the navigation bar will reject the changes. By pressing Delete the whole scenario will be deleted. A scenario can only be deleted when it is not used in an auction otherwise the button Delete will not be available. In this case also a save will only refer to the changes at "Name" "Tag", "Date" and "Own" but not to changes at the bid structure. The bid structure will not be editable if a bid scenario is used in an auction scenario.

03.3.4 Duplicate a Bid Scenario

As mentioned at saving and deleting bid scenarios a bid structure is only editable if the bid scenario is not used in any auction scenario. The button Duplicate copies the whole bid scenario (including the bids) and saves it under new ID. The original scenario will not be touched and the new scenario will be editable in all ways because it is not used in any auction scenario.

03.3.5 Search and Select a Bid Scenario

To search for a bid scenario go to navigation bar Bid and List. The "Bid scenario selection view" (Figure 20) is displayed.

03.3.5.1 Set up the Search Filter

First a filter for the bid scenarios can be defined (On the left side under "Search for a bid scenario" at Figure 20). A filter includes the name, tags, dates and products. A scenario is only shown in "Matching scenarios" if it includes these phrases defined by the filter. It can also be declared if a scenario has to match all of the tags or only one to be shown in the list. Additionally only the own or the market scenarios can be shown. At "Matching scenarios" the scenarios are ordered by an internal number (ID) depending on the order of construction.

03.3.5.2 Select a Bid Scenario

A bid scenario is selected by a click on it in the "Matching scenarios" list. After this the bid scenario quick information is presented. By clicking Edit the "Bid edit view" will be opened and the scenario can be edited.

Figure 20: Bid scenario selection view

03.3.6 Bid Generator

Another possibility to add bids is to generate bids by statistical behaviors. The bid generator provides this powerful functionality. To open the bid generator the button Generate has to be pressed at "Bid scenario edit view" (Figure 18). It opens the bid generator (Figure 21 & Figure 22). The bid generator is basically split up into two methods, region and path wise generation of bids.

03.3.6.1 General Settings

First the method has to be selected. The method is either region wide (see 03.3.6.3) or path wise (see 03.3.6.2).

As next step the product for which bids should be generated has to be declared.

The third part is to select the statistical method. Four statistical methods are available, flat distribution, normal distribution, concave and convex distribution. Depending on the distribution method the distribution parameter has to be defined. For a detailed definition of the statistic methods see "Appendix A – STATISTIC METHOD DESCRIPTION".

The last part of the general settings are the bid volumes. The generated bids will have the volumes (in MWh) defined in this field. Different volumes can be separated by ";". The volumes must be whole numbers greater than zero. There will be an equal deviation of the bid volumes to the bids.

03.3.6.2 Path Wise Bid Generation

At a path wise generation (Figure 21) the source and the sink of the path have to be defined. Also the price level on which the distribution will be laid (in case of a flat distribution all prices are on that level) has to be defined. The requested volume defines how many volume the bids should have in sum. By pressing Generate the bids will be generated.

Figure 21: Bid generator with path wise view

03.3.6.3 Region Wide Bid Generation

The region wide generation (Figure 22) is a little bit more sophisticated. For a region wide generation for each path a price level and a capacity have to be declared. In a way for better overview the price levels can be derived from the market prices and the capacities from a PTFD matrix.

With the defined market prices in the "Market prices" table the price levels (approximated market clearing price) for the paths will be calculated by the difference between the two market prices. The approximated MCP will be calculated by pressing the button Update next to the table.

On the right side by selecting a PTFD the approximated capacities can be defined. The capacities for the calculation will only be taken when the price on this path is greater than zero.

The auto update option enables that the depending matrices will automatically be updated if the data in the corresponding table / matrix changes.

By pressing Generate the bids will be generated.

Figure 22: Bid generator with region wide view


03.3.6.4 Submit or Drop the Bids

The generated bids will be submitted by pressing the button Submit. Afterwards the view changes to the "Bid scenario edit view". If only Back will be pressed the generated bids will be rejected while going back to the "Bid scenario edit view". In any case the changes will be finally submitted by saving the bid scenario by pressing Save at the "Bid Scenario Edit View (Figure 18, see 03.3.3).

03.4 Auction – Auction Scenarios

There are two different auction types. First a full day auction that auction's a full day and as second a single PTDF auction that will auction only one single PTDF.


Figure 23: Minimized auction flow screen



03.4.1 Set Up an Auction Scenario

A new auction scenario can be generated by going to Auction and then to New in the navigation bar. The "Auction scenario screen" will be opened. First the auction flow type has to be indicated (either full day auction or single ptdf auction) (Figure 24). Afterwards the PTDF(s) and bid scenarios have to be selected as well as import and export limits can be defined.

Figure 24: Auction functionality panel



03.4.1.1 Select the PTDF

The PTDFs are selected to a date. If there are PTDFs for the selected day in case of a full day auction all PTDFs will be match to the corresponding product and for all of these PTDFs the auction will be calculated.

In case of a single PTDF auction one of the PTDFs of the list has to be selected (by marking it). In this case the matching monthly and yearly PTDFs will be shown too. The auction will be calculated for the selected PTDF.

Figure 25: PTDF selection panel



Select PTDFs

PTDF's

February 2011

Sun	Mon	Tue	W...	Thu	Fri	Sat
		1	2	3	4	5
06						
07	6	7	8	9	10	11
08	13	14	15	16	17	18
09	20	21	22	23	24	25
10	27	28				

Year: 2011

Day: 2011 / 2 / 11 - H01

Day: 2011 / 2 / 11 - H02

Day: 2011 / 2 / 11 - H03

Day: 2011 / 2 / 11 - H04

Day: 2011 / 2 / 11 - H05

Day: 2011 / 2 / 11 - H06

Day: 2011 / 2 / 11 - H07

Day: 2011 / 2 / 11 - H08


Day: 2011 / 2 / 11 - H09

Day: 2011 / 2 / 11 - H10

03.4.1.2 Select the Bid Scenarios

The bid scenarios will also be selected over a calendar. Each bid scenario has dedicated dates (see 03.3.1.2) and on that dates it will be shown in the calendar. If a bid scenario has no date it will not be shown. At "Available scenarios" all scenarios will be shown for the selected date. By selecting a scenario and pressing Add under to the table the scenario will be added to the "Selected scenarios" list. It is possible to add multiple scenarios from different dates to the "Selected scenarios" list. By selecting a bid scenario in the "Selected scenarios" list and pressing Delete the bid scenario will be removed from this auction scenario.

Figure 26: Bid scenario selection panel



Select Bid

Bid scenarios

February 2011

Sun	Mon	Tue	W...	Thu	Fri	Sat
		1	2	3	4	5
06						
07	6	7	8	9	10	11
08	13	14	15	16	17	18
09	20	21	22	23	24	25
10	27	28				

Available scenarios

ID	Name	Own
36	neu	<input type="checkbox"/>

Selected scenarios

ID	Name	Own
1	sc001	<input checked="" type="checkbox"/>

Add Delete

03.4.1.3 Define Import and Export Limits

There is also the possibility to use limits for single market areas. An import limit defines the maximum capacity that can be imported to a market area, an export limit the maximum capacity that can be exported. At an auction it can be defined if limits should be used or not. By marking "Use Limits" the defined limits in the table below will be used. In the table for each market area an import and an export limit can be defined. The maximum possible limit for one area is 100.000 MW, no limit is defined by a negative value and shown as INF (infinite). Figure 27 shows the limit definition screen of the auction scenario.

Figure 27: Import / Export limit selection panel

Area	Max Import	Max Export
DE_AT	INF	INF
PSEO	30	INF
ELES	50	INF
MAVIR	INF	INF
CZ_SK	20	INF

03.4.1.4 Run the Auction

If at minimum one PTDF and one bid scenario is selected the auction scenario can be calculated by pressing the button Run Auction at "Auction Functions". This will start the internal process of the model generation and after the model is fully generated it will be calculated by an external program called GAMS (see 02.4). During the calculation next to the button Run Auction the text "working ..." will be shown (Figure 28). An exact forecast of the calculation time is not possible because it is non linear dependent on the given bids per product, the size of the PTDFs and other constraints. It can be seconds for a "short" model up a few minutes in case that many data have to be handled. For a more detailed view on the calculation times a short study was done and can be seen in "Appendix B – CALCULATION TIMES".

Figure 28: Auction scenario screen while calculation

03.4.1.5 Show the Results

After the calculation the button Show Result is available (Figure 29). By a click on it the results will be shown. (See 03.5)

Figure 29: Auction scenario screen after calculation

03.4.1.6 Save the Auction Scenario

In the lower section of the "Auction Functions" (Figure 24) the save section is displayed. By pressing Save or Save as the auction scenario will be saved. If an existing auction scenario has been opened Save as saves a copy of the original scenario with the done changes and Save will overwrite the original.

Figure 30: Auction scenario save section

The saved parts are the auction type (full day or single PTDF), in case of a single PTDF the selected PTDF, in case of a full day the date, the selected bid scenarios, the save name and if the auction was calculated and has a result.

After the auction scenario has been saved the sensitivity analysis panel will be shown (see 03.6) and sensitivity analyses can be calculated.


03.4.1.7 Close an Auction Scenario

If at minimum one sensitivity analysis (see 03.6) is calculated for the auction scenario the auction scenario will not be editable anymore. This is done to keep the data consistent because if afterwards the auction scenario will be changed the sensitivity analyses would not correspond to the auction scenario anymore. In this case Save As generates an editable copy of the auction scenario without the sensitivity analyses corresponding to the original auction scenario.

03.4.2 Open a Saved Auction Scenario

A saved auction scenario can be opened over the screen available under Auction and then List. The "Auction list view" (Figure 31) will be shown. By selecting an auction scenario in the list and clicking Open or making a double click the auction scenario will be opened and the "Auction scenario view" will be shown with the corresponding data.

Figure 31: Auction scenario list



List of all saved auctions


Id	Name	PTDf Date	ScenarioIDs	Type	Results
1	name1	2010/11/10	1,2	FULL DAY	<input type="checkbox"/>
6	New Auction1	2010/7/25	2	FULL DAY	<input type="checkbox"/>
7	New Auction6	2010/7/25	1,2,3	FULL DAY	<input type="checkbox"/>
8	New Auction8	2010/7/23	1,2	FULL DAY	<input checked="" type="checkbox"/>
9	New Auction6	2010/7/2	1,2,3	FULL DAY	<input checked="" type="checkbox"/>
11	New Auction	2010/7/3		FULL DAY	<input type="checkbox"/>
12	New Auction	2010/7/1	2	FULL DAY	<input type="checkbox"/>
13	New Auction	2010/7/1	2,1	SINGLE PTDf	<input checked="" type="checkbox"/>
14	BigAuction	2010/4/1	4	FULL DAY	<input checked="" type="checkbox"/>
15	big one	2010/4/1	4	FULL DAY	<input checked="" type="checkbox"/>
16	big one single	2010/4/1	5	SINGLE PTDf	<input checked="" type="checkbox"/>
17	CalTimeSingle	2010/7/1	4	SINGLE PTDf	<input type="checkbox"/>
18	month001	2010/7/1	8	SINGLE PTDf	<input checked="" type="checkbox"/>
19	month2	2010/7/31	8	SINGLE PTDf	<input checked="" type="checkbox"/>
20	month3	2010/7/31	8	SINGLE PTDf	<input checked="" type="checkbox"/>
21	test_model	2010/4/1	1	SINGLE PTDf	<input type="checkbox"/>
22	test_model	2010/4/1	1	SINGLE PTDf	<input checked="" type="checkbox"/>
23	New Auction123	2010/10/1	8	SINGLE PTDf	<input checked="" type="checkbox"/>
24	New Auction	2010/10/11		SINGLE PTDf	<input type="checkbox"/>
25	New Auction	2010/10/11		FULL DAY	<input type="checkbox"/>
26	New Auction	2010/10/11		FULL DAY	<input type="checkbox"/>
27	New Auction	2010/10/1	8	SINGLE PTDf	<input checked="" type="checkbox"/>

Open Delete

03.5 Results

The results of a calculated auction are available by pressing Show Result at the "Auction scenario view" (Figure 24). Different views and selections are available for an auction at the result section (Figure 32).


Figure 32: Result view



03.5.1 Element Selections

It is possible to select the elements which should be presented in the single tables (Figure 33). It differs in bid scenarios, products, areas as source market areas and areas as sink market areas. By selecting the desired elements in the tables the results for these elements will be shown. In case of multi selection some elements must be aggregated to receive a significant result.

Figure 33: Selection region at result view



03.5.2 Select the View

Seven views are available: bid table, bid graph, path, source, sink, full and product view. The single view can be selected by selecting it in the combo box on the upper side of the view.

03.5.2.1 Bid Table View

The bid view (Figure 34) shows a table with all bids used in the auction (see 03.4.1.2). For each bid additional to the data shown in the "Bid table" (see 03.3.2.3), the accepted volume, the market clearing price (MCP) and the approximated payment value is shown. The payment value is calculated as:

$$\text{MCP} * \text{Accepted Volume} * \text{Hours of the Product}$$

This is only an approximation. For a year a standard year (and not a leap year) is taken and for a month a 30 days month is taken. So the payment value can be imprecise. The maximum deviation is 2 days in case of February and this will be 6.67% (1 day of a leap year are 0.23%). A detailed view on this issue is shown in the section products (see 03.7.3).

Figure 34: Result table view for the bids

Views
Bid view ▼

BID LIST


PRODUCT	SCENARIO	SOURCE	SINK	REQUES..	ACCEPTE..	PRICE	MCP	PAYMENT..
H01	1	DE_AT	CZ_SK	5	0	3.06	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	3.06	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	3.02	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	3.02	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	1.96	17.27	0.00
H01	1	DE_AT	CZ_SK	10	0	1.90	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	1.77	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	1.57	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	1.45	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	1.35	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	1.25	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	1.15	17.27	0.00
H01	1	DE_AT	CZ_SK	10	0	1.07	17.27	0.00
H01	1	DE_AT	CZ_SK	5	0	1.05	17.27	0.00
H01	1	DE_AT	CZ_SK	85	0	0.01	17.27	0.00
H01	1	DE_AT	MAVIR	10	10	19.50	13.76	137.60
H01	1	DE_AT	MAVIR	10	10	17.39	13.76	137.60
H01	1	DE_AT	MAVIR	10	10	15.64	13.76	137.60
H01	1	DE_AT	MAVIR	5	5	15.40	13.76	68.80
H01	1	DE_AT	MAVIR	10	10	15.26	13.76	137.60
H01	1	DE_AT	MAVIR	5	5	14.88	13.76	68.80
H01	1	DE_AT	MAVIR	15	15	14.76	13.76	206.40
H01	1	DE_AT	MAVIR	20	20	14.51	13.76	275.20
H01	1	DE_AT	MAVIR	25	25	14.26	13.76	344.00
H01	1	DE_AT	MAVIR	5	5	14.14	13.76	68.80
H01	1	DE_AT	MAVIR	5	5	14.10	13.76	68.80
H01	1	DE_AT	MAVIR	30	30	14.01	13.76	412.80
H01	1	DE_AT	MAVIR	35	25	13.76	13.76	344.00
H01	1	DE_AT	MAVIR	5	0	13.52	13.76	0.00
H01	1	DE_AT	MAVIR	10	0	13.52	13.76	0.00
H01	1	DE_AT	MAVIR	40	0	13.51	13.76	0.00
H01	1	DE_AT	MAVIR	10	0	13.29	13.76	0.00
H01	1	DE_AT	MAVIR	5	0	13.10	13.76	0.00
H01	1	DE_AT	MAVIR	10	0	13.01	13.76	0.00
Sum								

☐ Only awarded bids Save as

03.5.2.2 Bid Graph View

The bid graph view shows the bids for one source sink combination as graph. The accepted bids are shown in green the not accepted bids in red. Figure 35 shows the bid graph view for the border from DE_AT to PSEO.


Figure 35: Result graph view for the bids



03.5.2.3 Path View

The path view (Figure 36) displays an overview of the result for each path (source sink pair) in a matrix. Three elements can be displayed: the requested volume, the accepted volume and the market clearing price. The element can be selected over the drop down menu. In case of multiple product selection the market clearing price cannot be calculated and shown because there are different MCPs for different products on the same path. In the upper section the results are shown as table and in the lower section as graph.

Figure 36: Result view for the paths




03.5.2.4 Source View

The source view (Figure 37) displays the results for one source to all sinks. The source can be selected over the drop down menu. The elements in the drop down list depend

on the selected source areas. For each source-sink combination the requested volume, the accepted volume and the market clearing price is shown. At the lower area of the view the results are shown as graph.


Figure 37: Result view for one source and all sinks



03.5.2.5 Sink View

The sink view (Figure 38) displays the result for all sources to one sink. The sink can be selected over the drop down menu. The elements in the drop down list depend on the selected sink areas. For each source-sink combination the requested volume, the accepted volume and the market clearing price is shown. At the lower area of the view the results are shown as graph.

Figure 38: Result view for all sources and one sink



03.5.2.6 Full View

The full view (Figure 39) displays the results for all existing paths, products and scenarios. The entries are sorted by product, bid scenario, source area and sink area and show the requested volume, the accepted volume and the MCP for this result. By pressing Aggregate under the selected elements this elements will be summed up. In case of multiple source / sink areas or products the MCPs cannot be calculated.

Figure 39: Result view for the full path results

Views
Full view

Full View
Result Table

Product	Scenario	Source	Sink	Req	Acc	Mcp
H01	1	MAVIR	CZ_SK	0	0	3.51
H01	1	MAVIR	DE_AT	25	25	0.00
H01	1	MAVIR	ELES	0	0	0.00
H01	1	MAVIR	PSEO	0	0	0.00
H01	1	CZ_SK	MAVIR	554	554	0.00
H01	1	CZ_SK	DE_AT	125	125	0.00
H01	1	CZ_SK	ELES	40	40	0.00
H01	1	CZ_SK	PSEO	10	10	0.00
H01	1	DE_AT	MAVIR	1151	175	13.76
H01	1	DE_AT	CZ_SK	165	0	17.27
H01	1	DE_AT	ELES	1265	87	10.37
H01	1	DE_AT	PSEO	0	0	6.13
H01	1	ELES	MAVIR	0	0	3.39
H01	1	ELES	CZ_SK	30	0	6.90
H01	1	ELES	DE_AT	65	65	0.00
H01	1	ELES	PSEO	0	0	0.00
H01	1	PSEO	MAVIR	0	0	7.63
H01	1	PSEO	CZ_SK	0	0	11.14
H01	1	PSEO	DE_AT	0	0	0.00
H01	1	PSEO	ELES	0	0	4.25


Sum

Save as

03.5.2.7 Product View

The product view (Figure 40) displays the results for different products and one path (source-sink combination). In the upper section for each product the requested volume, the accepted volume and the market clearing price is shown in a table and in the lower section the result is shown as graph.


Figure 40: Result view for the products



03.5.2.8 Sum the Result Elements

In the result table a section can be selected by marking it. For the selected region the sums of the single columns or elements are calculated and shown under the table in the fields labeled by "Sum". Figure 41 shows a schematic illustration.


Figure 41: Summing at result view



03.6 Sensitivity Analysis

One of the major features of the software is the execution of sensitivity analysis. The sensitivity analysis shows the changes of the results by different additional allocated amounts of capacity at one path. The sensitivity analysis is part of an auction scenario (Figure 23) and illustrated in Figure 42.

Figure 42: Sensitivity analysis panel of an auction scenario



03.6.1 Setup of Sensitivity Analysis

A sensitivity analysis can only be done for requested volumes at one border in one direction. The definition of the border and the direction is done by selecting one market area as source area and one as sink area. Afterwards the start volume and the additional requested volume has to be defined and the step size this capacity should be approximated declared. E.g. if the start volume is 0 and the additional requested volume is 100 and the step size is 10 then the sensitivity analysis will calculate 11 steps with additional amounts of 0, 10, 20, 30, 40, 50, 60, 70, 80, 90 and 100 MW.

03.6.2 Run of Sensitivity Analysis

By pressing Run the sensitivity analysis is calculated. For each PTDF of the auction a own sensitivity analysis is calculated. At each step of each PTDF a full auction (single PTDF auction, see 03.4) will be calculated. E.g. for a full day (24 PTDFs) and 10 steps, 240 single PTDF auctions will be calculated. This might take a long time. During the calculation next to the button Run the actual progress is shown. It shows for which PTDF and for which additional amount the auction is actually calculated. After the calculation the sensitivity result will be shown in the "Calculated sensitivity analysis" list.

If in minimum one sensitivity analysis is performed for an auction scenario the auction scenario will be closed (see 03.4.1.7). This means that the PTDFs and the bid scenarios an auction scenario is calculated for cannot be changed anymore.

03.6.3 Open a Calculated Sensitivity Analysis

If a sensitivity analysis is calculated for an auction scenario the auction scenario cannot be changed anymore. The calculated sensitivity analyses are shown at "Calculated sensitivity analysis". In the list they are separated by the sensitivity analysis scenarios and for each scenario and each PTDF a sensitivity analysis exists. One single sensitivity analysis has to be selected and by pressing the button Open or a double click the results of this sensitivity analysis are shown (see 03.6.5).


03.6.4 Delete a Sensitivity Analysis / a Sensitivity Analysis Scenario

A sensitivity analysis can be deleted by selecting it at "Calculated sensitivity analysis" and pressing the button Delete. It is possible to delete one single sensitivity analysis or a whole sensitivity analysis scenario by selecting the corresponding element in the list. If no sensitivity analysis exists for an auction scenario the auction scenario will be editable again.

03.6.5 Sensitivity Analysis Results

After opening a sensitivity analysis by pressing the button Open (03.6.3) the "Sensitivity analysis result" screen is shown (Figure 43). There are four different views (03.6.5.2 to 03.6.5.5) available. They are split up into "Step comparisons views" and "Single step views". Step comparison views compare a part of the results over the different steps and the single step view shows the whole result for one step.

Figure 43: Sensitivity analysis result panel with the step comparison path view



03.6.5.1 Select the View and the View Selections

At the "View selection" section the desired view can be selected. Depending on the selected view at "Steps", "Source" and "Sink" different selections are possible. At the step comparison views the steps that should be compared can be selected by marking them, at single step view only on step can be selected. Also the sources and the sinks that should be shown must be selected. In case of the step comparison path view only one source and only one sink can be selected, in all other cases a multiple selection of the areas is possible.

03.6.5.2 Step Comparison – Path View

The step comparison path view displays the results for on path over the selected steps. The steps that should be shown have to be selected at Selections / Steps and afterwards one path must be selected by selecting one source and one sink. In the table the requested volume, the accepted volume and the market clearing price for this path is shown for each step.

03.6.5.3 Step Comparison – Element View

The step comparison element view compares one element (Requested volume, accepted volume or MCP) over the selected steps and paths. The table has a column for each path in which the results for each step is displayed.

03.6.5.4 Step Comparison – Full View

The full view displays all elements of the result set in a table. It can be selected for which steps, sources and sinks the requested volume, the accepted volume and the market clearing prices should be shown. The table is sorted by step, source and then by sink.

03.6.5.5 Single Step – Path View

The single step path view displays the overview results for all paths of one step. It correlates to the result path view (see 03.5.2.3) and shows the requested volume, the accepted volume or the MCP for all paths in a matrix.

03.7 Data Management and Presettings


Some of the used and stored data can be personalized and initialized. This function provides a faster and better usage of the main program functionalities. Also the not editable data can be shown to get a fast overview on the data used in the background of the program (e.g. the existing products).

03.7.1 Manage the Market Areas

A market area consists of market zones. The binding of the zones to the market area cannot be managed from the program. If there are changes in this structure this has to be managed external in the data structure. But for load flow based auctions only the market areas are meaningful. The existing market areas can be shown in [Data](#) and [Market Areas](#) (Figure 44). For a better use of the program the order of the market areas can be changed. This can be done by selecting a market area in the table and pressing either the button [Up](#) or [Down](#). The market area will be shifted one position up or down in the list. In every view multiple market areas occur, the areas will be sorted by this order.

In addition a major source area and a major sink area can be selected. In every case source or sink can be chosen the predefined major will be preselected. This smoothes the usage if e.g. a trader is only concerned about one border.


Figure 44: Market area management



03.7.2 Market Prices

The market prices are the actual energy price approximations of the user in the single market areas. The market prices are used for the calculation of the approximated market clearing prices at the bid generator (see 03.3.6). For an easier use they can be predefined at [Data](#) and [Market Prices](#) (Figure 45), so that they have not to be inserted each time for new. Actually there can only be one price level stored.

Figure 45: Market price management



03.7.3 Products

The products used in the program can be shown under Data and Products (Figure 46). They are split up into auction-able and bid-able. Auction-able are all products that can be used for an auction, bid-able all products for which bids can be set up in a bid scenario. This differentiation has the advantage because it is not useful to differ bids for nearly equal products. E.g. for a month with 30 or 31 days it should be able to use the same bids of a bid scenario.

Actual there can be bids for each hour of the day (H01 to H24) and for monthly or yearly auctions bids with the product BASE are used.

Also another simplification has been done. There is only one monthly auction-able product (instead of four) and one yearly product (instead of two). This only affects the payment value (See 03.5.2.1) of a bid in the results (because they are multiplied by the hours) in a constant way. The maximum error deviations of the payment value that will occur are two days on a "normal" February with 28 days. In that case the payment value will be 6.67% to high. The most likely deviation occurs on 31 days months. In that case the payment value will be 3.33% to low. In a leap year the error against a normal year is 0.23%. **The MCP and the accepted volumes of a result are NOT affected.**

Block bids and linked bids are not implemented yet as they are also not used within CAO IT.

Figure 46: Product list

Code	Name	Type	Hours	Bid able	Auction able
BASE	For Monthly an...	Yearly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H01	Hour 01 (00:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H02	Hour 02 (01:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H03	Hour 03 (02:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H04	Hour 04 (03:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H05	Hour 05 (04:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H06	Hour 06 (05:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H07	Hour 07 (06:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H08	Hour 08 (07:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H09	Hour 09 (08:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H10	Hour 10 (09:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H11	Hour 11 (10:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H12	Hour 12 (11:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H13	Hour 13 (12:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H14	Hour 14 (13:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H15	Hour 15 (14:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H16	Hour 16 (15:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H17	Hour 17 (16:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H18	Hour 18 (17:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H19	Hour 19 (18:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H20	Hour 20 (19:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H21	Hour 21 (20:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H22	Hour 22 (21:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H23	Hour 23 (22:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
H24	Hour 24 (23:00)	Hourly	1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
MONTH	30 Days Month	Yearly	720	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Y	Year	Yearly	8760	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

03.7.4 Predefine Import and Export Limits

The import limits maybe used in auctions can be predefined at Data and I/E Limits (Figure 47). For each market area and import and an export limit can be defined. The

maximum of the limit is limited with 100.000 MW. Not limit is defined by a negative value and shown as INF (infinite). The defined limits will be automatically written to the "Limit Screen" at auctions.


Figure 47: Standard import and export limits



03.7.5 Predefine Import Paths

Standard import paths can be defined under Setting und Setting (Figure 48). The paths can be defined for importing PTDFs and bid scenarios from external files, as for saving files out from the system. In all cases the local file system will be opened. The standard path defines at which location the file system will be opened. This allows the user that always the same directory will be opened for the same process. For the definition of the standard path the button Select next to "PTDF import path / Bid import path / Save as path" has to be pressed. The file system opens and a directory can be chosen. With a click on Save the changes will be submitted.

Figure 48: Standard path definition view



03.8 Other Functionality

03.8.1 Export the Shown Tables

The shown tables can be exported from the system and saved as .csv file. This is possible if the button Save as exists under a table or a matrix. The button Save all will appear if there are more than one table selections possible. By a click on the button the local file-system opens and the save directory and save name can be defined. Save all saves all possible tables of the view in one file, Save as the one that is currently shown.

03.8.2 Block Functionality

In special cases some elements have to be blocked to keep the data consistent. In this case the element is not editable anymore. Bid scenarios have to be blocked if they are used in auction scenarios. Figure 49 shows a blocked bid scenario. The buttons Delete, Generate and Import are not available. Auction scenarios have to be blocked if there exists a sensitivity analysis for this auction scenario. In both cases a copy without the

corresponding elements can be applied. For a bid scenario this is done by the button Duplicate (see 03.3.4) and for an auction scenario with the button Save As (see 03.4.1.6).

Figure 49: Blocked Bid Scenario

PTDF

Now

Bid Scenario

List

Auction

Data

Setting

Bid scenario

Scenario characteristic

Name : empty matrices marketprices

Tag :

Add

Dedicated tags

Date :

Add

Dedicated dates

2011/03/11

Own bid scenario

Back

Delete

Save

Duplicate

Bid informations

Bids quick view

Product	Bid count
H01	777
H02	679
H03	887
H04	908

Show

Generate

Import

Path informations

Bid count on a path

	PSEO	MAVIR	ELES	DE_AT	CZ_SK
PSEO	0	54	83	97	73
MAVIR	0	0	0	53	0
ELES	0	67	0	97	80
DE_AT	0	0	0	0	0
CZ_SK	0	53	0	125	0

Sum of requested volume per path

	PSEO	MAVIR	ELES	DE_AT	CZ_SK
PSEO	0	2700	4150	4600	3650
MAVIR	0	0	0	2650	0
ELES	0	3350	0	4850	4000
DE_AT	0	0	0	0	0
CZ_SK	0	2650	0	6250	0

Average price on a path

	PSEO	MAVIR	ELES	DE_AT	CZ_SK
PSEO	0.00	8.37	7.41	11.00	7.82
MAVIR	0.00	0.00	0.00	2.40	0.00
ELES	0.00	0.99	0.00	3.38	0.43
DE_AT	0.00	0.00	0.00	0.00	0.00
CZ_SK	0.00	0.57	0.00	2.98	0.00

Auctions used

Auctions bid scenario is used 4

04 CONTACT INFORMATION

General questions

tradertool@riecado.at or
andreas.wolf@riecado.at

Technical support

stefan.hartlieb@riecado.at
+43 (0)1 319 07 01-374

Homepage

www.riecado.at

APPENDIX A – STATISTIC METHOD DESCRIPTION


This section gives a detailed view on the available statistical methods used to generate bids with the bid generator (See 03.3.6). There are four different statistic distributions available:

- Flat distribution
- Normal distribution
- Convex distribution
- Concave distribution

Flat Distribution

A flat distribution allots all elements at the same level. The level which remains constant is the only parameter that is used for this distribution. Figure 50 shows a schematic illustration of a flat distribution.


Figure 50: Schematic illustration of a flat distribution



Normal Distribution

The most likely distribution for market clearing prices is the normal distribution. It allots the elements by a gaussian function. The two parameters for a gaussian function are the mean and the variance. The mean defines the standard price level and the variance the spreading of the elements. In the bid generator the variance can be inserted relatively to the mean. In that case the variance is defined by $\text{mean} * 1/\text{value}$. E.g. if the price level / MCP (=mean) is 100 and the inserted value is 10 then the variance is 10 (100 divided by 10). That means that the most values will range between 90 and 110 (68%) and 95% of the values between 80 and 120. Mathematically there is no upper or lower bound. Theoretically a market price can be infinity too. A lower bound is defined by zero, because there are no negative bids existing. Figure 51 shows the schematic price levels for a normal distribution. The most prices are around the center at one level. On the upper and lower range of the scope there are a few extreme values.


Figure 51: Schematic illustration of a normal distribution



Convex Distribution

A convex distribution most likely simulates a market order. In that case a few bids are very high but after the highest bids a very hard decay will occur. The distribution is defined by a saddle point and a maximum. The saddle point is equal to the price level and the maximum is defined as multiplier of this level. E.g. if the price level is defined with 100 and the value for the maximum is 4 the maximum occurring price will be up to 400 (4×100). The most values of this distribution will be between the saddle point and zero. The upper bound of this distribution is the maximum value the lower bound is zero. Figure 52 shows a schematic illustration of a convex distribution.

Figure 52: Schematic illustration of a convex distribution




Concave Distribution

A concave distribution has a slow decrease on the upper side of the saddle point and a fast at the lower side of the saddle point. The distribution is defined by two parameters, the saddle point and the maximum value. The saddle point is defined by the price level and the maximum value is defined relatively to the corresponding price level (price level multiplied by the value). E.g. if the price level (=saddle point) is defined by 100 and the maximum value is defined by 1.3 the maximum price will be 130 (100×1.3). The generated prices will be between 130 and zero. The most values

between 130 and 100 and fewer between 100 and zero. Figure 53 shows a schematic illustration of a concave distribution.

Figure 53: Schematic illustration of a concave distribution



APPENDIX B – CALUCLATION TIMES

The calculation where done on a standard laptop (Intel Core2 CPU T7400 2.16GHz, 2GB RAM). This is done because an exact approximation of the calculation time before calculating the model is not possible. This section provides a short overview how long the calculation could take in case of different amount of data's. The results are split up by the PTDF count (how many PTDFs), PTDF length (how many branches in average per PTDF), the general bid count, the range of bid counts per product, the range of bid counts per path, the range of volume per path and the calculation time.

Figure 54 : Overview on calculation times

PTDF count	Avg Branches	Bids	Bids per product	Bids per path	Volume per path	Time
1	600	200	200	10	200	2 sec
1	600	1000	1000	50	1000	9 sec
4	600	4000	1000	50	1000	35 sec
4	600	800	200	10	200	6 sec
4	600	452	(1-374)	(0 - 137)	(0 - 1265)	3 sec
1	1500	200	200	10	200	5 sec
1	1500	1000	1000	50	1000	24 sec
23	1500	4600	200	10	200	2 min 37 sec
23	1500	23000	1000	50	1000	10 min 20 sec
23	1500	471	(1-374)	(0 - 137)	(0 - 1265)	47 sec

APPENDIX C – SHORT TERMS

AMF – Available Maximum Flow

CAO – Central Allocation Office

CEE – Central Eastern Europe

ECAMT – Enhanced Capacity Auction Management Tool

GAMS – General Algebraic Modeling System

MCP – Market Clearing Price

PTDF – Power Transfer Distribution Factor

TMF – Total Maximum Flow